



TTAP-CV

Installation and Start-Up Instructions

System Requirements

Operating System	Minimum Requirements	Recommended Requirements
Windows 7 Ultimate, Professional, Home Premium*	CPU: 1 GHz or faster RAM: 1 GB DirectX 9 graphics device with WDDM 1.0 or higher driver, CD-ROM drive	CPU: 1 GHz or faster RAM: 2 GB DirectX 9 graphics device with WDDM 1.0 or higher driver, CD-ROM drive
Windows Vista Ultimate, Business, Home Premium (SP 2)*	CPU: 1 GHz or faster RAM: 1 GB 1024 × 768 or higher resolution video adapter and display, CD-ROM drive	CPU: 1 GHz or faster RAM: 2 GB 1024 × 768 or higher resolution video adapter and display, CD-ROM drive
Windows XP Professional, Home Edition (SP 3)*	CPU: Pentium III 700 MHz or faster RAM: 256 MB 1024 × 768 or higher resolution video adapter and display, CD-ROM drive	CPU: Pentium III 700 MHz or faster RAM: 2 GB 1024 × 768 or higher resolution video adapter and display, CD-ROM drive
Mac OS X v10.6*	CPU: Intel-based Mac RAM: 1 GB CD-ROM drive	CPU: Intel-based Mac RAM: 2 GB CD-ROM drive
Mac OS X v10.5.7*	CPU: PowerPC G4 (867 MHz+), Power PC G5, Intel-based Mac RAM: 512 MB CD-ROM drive	CPU: Intel-based Mac RAM: 2 GB CD-ROM drive
Mac OS X 10.5 Leopard*	CPU: PowerPC G4 (867 MHz+) G5 Intel-based Mac RAM: 512 MB RAM Display: Super VGA (1024 × 768) video, CD-ROM drive	
Mac OS X 10.4.11 Tiger*	CPU: PowerPC, G4, or G5 Intel-based Mac RAM: 256 MB RAM Display: Super VGA (1024 × 768) video, CD-ROM drive	

*Version stated is the minimum requirement. TTAP-CV may also work with later versions certified by FileMaker, Inc.

Networking

CP/IP: limited to nine simultaneous FileMaker client connections; each client requires a licensed copy of the FileMaker software.

Use FileMaker Server 11 for increased capacity. FileMaker Pro 11 supports Internet Protocol Version 6 (IPv6) addresses, as well as IPv4 addresses. Any computer accessing FileMaker Pro files over a network will need to have a licensed installation of FileMaker Pro or FileMaker Pro Advanced versions 9, 10, or 11.

Installing

Windows XP/Vista/7

Insert the TTAP-CV CD-ROM into your drive. Locate the file TTAP setup.exe on the CD-ROM. Double-click the file and follow the on-screen directions. Upon completion of the installation, a TTAP.exe launch icon will appear on your desktop and in your Start Menu. Double-click the TTAP.exe icon to launch the program.

To uninstall the program, locate the Uninstall TTAP link in the TTAP folder in your Start Menu. Double-click the link and follow the on-screen directions.

Macintosh

Insert the TTAP CD-ROM into your drive. Locate the TTAP.dmg icon on the CD-ROM. Double-click the file. A disk image called Install TTAP OSX will appear on your finder, and a license agreement will appear. Accept the TTAP license agreement and then drag the TTAP folder from the Install TTAP OSX window to the Applications folder on your hard drive. Wait for all files to copy. To create an alias in your dock, drag the TTAP icon from the Applications folder to your dock. Double-click the TTAP icon to launch the program.

To uninstall the program, drag the TTAP folder from your Applications folder into the trash.

Starting

Windows XP/Vista/7

To launch the TTAP program, click on the TTAP.exe icon on your desktop or in the Start Menu.

Macintosh

Double-click the TTAP file in the TTAP folder.